

# **Enable Toggle**

Version: 20210602





### **Contents**

1	Prerequisite	2
2	Procedure	3
3	Result	5



### Contents

This topic describes how to enable toggles and configure common functions. After configuring, you can control the device on the app conveniently.



## 1 Prerequisite


You have created at least one product. For more information, see Create Products.



#### 2 Procedure


- 1. Log in to IoT Platform and enter My Products.
- 2. Select a product in **Developing**, and click **Entering to Develop** in the **Operation** list.
- 3. Following the page guide, select **Product Configuration** > **Quick toggle settings** > **Settings** to enter the **Settings** page.
- 4. On the **Quick toggle settings** page, select the operation types and replace the icons or configure the representation type.
  - **Quick toggle settings**: Quick toggle is a single-choice item. You can set the data point (DP) that is controlled by the quick toggle.
    - After the configuration is completed, on the device list page of the app, a switch button will appear on the right of the device. Furthermore, the device is shown in the widget of your mobile phone and can be woken up quickly.
  - **Common functions settings**: As a multiple-choice item, four common functions can be set.

After the configuration is completed, on the device list page of the app, an operation area of common functions will appear.



- 5. Click Save.
- Return to the development procedure, click **Device Panel**, and scan the QR code with the Tuya Smart app. Test the added quick toggle and common functions.








### 3 Result

Take a heater for example. If the quick toggle is enabled, when you test the product with the Tuya Smart app, the product is shown on the **My Home** page on the app. You can enable and disable the device.

• Example panel of the app is as follows:



{width=200px}

• Example widget panel of the mobile phone is as follows:






{width=200px}

Take a light bulb for example. After you configure the common **Switch Bool** online, you can unfold the drop-down list of the device on the **My Home** page on the app, and control the device. Example panel of the app is as follows:





{width=200px}



https://player.bilibili.com/player.html?aid=57736843